

Windows Mail

- Click the **Tools** menu.
- Click Accounts.
- Select your email account, and then click Properties.
- Click the **Servers** tab.
- Under **Incoming Mail Server** in the field labeled **Email Username** enter your full email address.
- Put a check next to "My server requires authentication"
- Click the **Settings** button.
- Select the option next to "Use same settings as my incoming mail server"

eneral Servers Connec	ction Security Advanced	Logon Information	
Server Information		O Use same settings as my incoming mail server	
My incoming mail server	is a POP3 server.	O Log on using	
Incoming mail (POP3):	mail.united.net	Account name:	
Outgoing mail (SMTP):	smtp.united.net	Password:	
Incoming Mail Server —		Remember password	
E-mail username:	tech@united.net	Log on using Secure Password Authentication	
Password:			ncel
	Remember password		incei
Log on using clear te	ext authentication		
O Log on using secure	password authentication	Note: Outgoing Mail Server wind	OW
🔘 Log on using auther	ticated POP (APOP)	becomes active once selecting the	he
Outgoing Mail Server —		Settings button.	
Wy server requires a			

Outlook Express (Windows 95/98/ME/2000/XP) & Outlook 2000+

- Click the Tools menu.
- Click Accounts
- Select your email account, and then click Properties.
- Click the **Servers** tab.
- Under **Incoming Mail Server** in the field labeled **Account Name** enter your full email address.
- Put a check next to "My server requires authentication"
- Click the **Settings** button.
- Select the option next to "Use same settings as my incoming mail server"

🗃 mail. united. net Properties 🛛 🔹 💽	Outgoing Mail Server 🛛 ? 🗙
General Servers Connection Security Advanced	Logon Information Output to the same settings as my incoming mail server
My incoming mail server is a POP3 server.	O Log on using Account name:
Outgoing mail (SMTP): smtp.united.net	Password:
Incoming Mail Server Account name: tech@united.net	Log on using Secure Password Authentication OK Cancel
Remember password Log on using Secure Password Authentication Outgoing Mail Server My server requires authentication Settings	Note: Outgoing Mail Server window becomes active once selecting the Settings button.
OK Cancel Apply	

(See Below)

<u>Mozilla Thunderbird</u>

- Click the email address in the panel on the left.
- •Click " View settings for this account."
- •Click Outgoing Server (SMTP) in the panel on the left.
- •Select your United Communication's email account.

- •Click **Edit.**
- Change Authenication method to Password, transmitted insecurely
- In the field labeled User Name enter your full email

(See Below)



	Account Settings	×		
▲ Local Folders Junk Settings	Outgoing Server (SMTP) Settings	t by selecting		
Disk Space	it as the Outgoing Server (SMTP), or you can use the default server from this list by selecting "Use Default Server".			
Copies & Folders	tech@united.net - smtp.united.net (Default)	A <u>d</u> d		
Composition & Addressing		<u>E</u> dit		
Junk Settings		D		
Synchronization & Storage		Remove		
Return Receipts		Se <u>t</u> Default		
Security				
Outgoing Server (SMTP)	Description: <not specified=""></not>			
	Server Name: smtp.united.net			
	Port: 587			
	User Name: tech@united.net			
	Authentication method: Password, transmitted insecurely			
	Connection Security: None			

	2	SMTP Server	
Settings			
Description:			
Server Name:	smtp.unit	ted.net	
Port:	587	Default: 587	
Security and A Co <u>n</u> nection se	uthenticati curity:	on None	~
Authentication	n method:	Password, transmitted insecurely	¥
User Na <u>m</u> e:		tech@united.net	
		OK Cancel	I